Document issue: 1

# Universal Joystick Programming Software: UJPS C++

V2.3.3 MANUAL

# **CONTENTS**

1	Introduction	4
2	The main principles	5
3	Setup	6
3.	5.1 External tools setup	6
3.	8.2 Building the application	6
4	A quick tour of the repository content	7
5	The main window	8
6	Hiding the real joysticks	10
6.	5.1 Devreorder	10
6.	5.2 WhiteKnight and ViGEm	10
7	Controllers plugins and monitoring apps	11
8	Remote controllers	13
8.	3.1 The theory	13
8.	A non-trivial example of what can be done	14
9	Create a profile	15
9.	Profile creation (by manual copy of a provided example)	15
9.	.2 Profile coding	15
9.	Profile compilation	17
10	What is under the hood	18
11	Layers and LayersCombos	19
13	1.1 LayersCombos as mapping filters	19
1:	1.2 Definition of a layer	19
1:	1.3 Registering shift buttons	19
13	1.4 How is computed the current layer	20
13	1.5 Constructing LayersCombo	20
12	Very basic axis and button mapping	22
13	Pre-defined actions	23
	13.1.1 Actions about buttons	23
	13.1.2 Actions about axes	24
	13.1.3 Actions about keyboard	25

1	3.1.4	4 Actions Chain, Delay and Sequence	26
1	3.1.5	5 Executing a custom function	26
14	Pr	e-defined mappings	28
14.1	. [	MappingStandard	28
14.2	2 [	MappingTempo	28
14.3	3 [	MappingAxis1	28
14.4		MappingAxis2	29
14.5	5 1	Mapping Axis Relative	29
14.6	6 1	Mapping Merge Axes	29
15	Pr	e-defined triggers for "standard mapping"	30
15.1	. 7	Triggers about axes	30
15.2	2 7	Triggers about buttons	30
16	Ot	her features	32
16.1		Axis trim and curves	32
16.2	? E	Button and axis locking	34
16.3	3 [	DoAction	34
17	Cu	rrent limitations and possible improvements	35
18	De	ependencies, credits, useful links	36
19	Ch	nanges notes	37
20	An	nnexes	39
20.1	. [	List of pre-defined triggers	39
20.2	2 L	List of pre-defined actions	39
20.3	3 L	List of pre-defined mappings	39
20.4	l k	Kevboards kevs names (Windows)	40

# 1 Introduction

#### Raw joysticks

By "raw joysticks" we mean joysticks used the simplest way: you plug your joystick, the system detects it and recognizes its buttons and axes. Then you go in the control options of your software / game and map the buttons and axes to "in-game actions / controls".

#### Programmable or programmed joysticks?

Beyond that there is also what we could call the "programmed joysticks". Many manufacturers call them "programmable joysticks", but I don't like this word as their joysticks are no more programmable as any other ones: they are programmable only because the manufacturer provides a software especially to program them, but there is nothing intrinsically related to the joystick. With UJPS C++ you will be able to program any joystick recognized by the system as a game controller.

#### Raw joysticks vs programmed joysticks

With raw joysticks you are limited to bind a button or axis to an "action" provided in the game control options menu. You cannot for example use one button for different actions without interference. Moreover the list of actions provided is not always suited for all types of controls, and with programmed joysticks you can do almost what you want between the physical joysticks and what sees the game. You can also make different joysticks interact with each other. This way you can create more ergonomic controls than just with raw joysticks. You can even sometimes fill gaps in the game controls by "programming" your joysticks.

#### The state of art

The manufacturers that do the most for "programmable" joysticks are CH and Thrustmaster (among general public joysticks). They both provide 2 different ways to program joysticks:

- One first and easier way using graphical interfaces (e.g. with CH Control Manager Programming Software, or Thrustmaster TARGET GUI)
- Another more advanced and less easy way using real programming or scripting (with CH scripts, or Thrustmaster scripts that are written in C programming language using a Thrustmaster provided functions library)

On the other side some free software exist to do so with joysticks of any brand but they are mainly based on graphical interfaces:

- UCR (Universal Control Remapper): https://github.com/evilC/UCR
- Joystick Gremlin: https://whitemagic.github.io/JoystickGremlin (+Python scripting)

#### UJPS C++

The present software allows to program joysticks of any brand, on Windows only, by programming in C++. Even if some knowledge of C++ is needed to get the best out of it, only basic C++ knowledge should be necessary to obtain good results. Anyway this software is quite similar to Thrustmaster scripts, is not harder than it, is a little more flexible and mostly allows to program any joystick.

# 2 The main principles

As all other software of this type, UJPS relies on virtual joysticks. These virtual joysticks are seen by the system just as real joysticks. The principle of UJPS is that the inputs of your joysticks are read by the software and the profile you programmed transforms these inputs into virtual joysticks actions or keyboard keystrokes. The profile is interchangeable and is chosen in the main window.




Figure 1: UJPS main principle

As a comparison, the Thrustmaster scripts allow only one virtual joystick and supports mouse inputs. UJPS profiles are in fact plugins (dll that can be load dynamically at runtime) that must be compiled before running them. Creating a profile is described in §6.

Since V2.0.0 you can also use remote controllers along the real joysticks. A remote controller is an application that connects (via network) to UJPS main app and exchange information with it. This application can be run on your local computer or on a mobile device, but you will have to write it yourself! It is comparable to Roccat Power grids or LEA extended input, but without the GUI editor, which makes this part of UJPS really less accessible to non-programmers users. More details are available in §8.

UJPS software uses external tools:

- Qt 5, a general C++ library
- vJoy, for virtual joysticks: http://vjoystick.sourceforge.net/site/
- QtGameController, a non-official Qt module from "openforeveryone", that I modified

When you use such joysticks programming tools, there is the usual issue of the dual inputs: the system and your game will see an event on both a real joystick and a virtual joystick. This should not be a problem when playing the game, but it can be really annoying when trying to assign the controls. To remedy to that I currently recommend you to use WhiteKnight from evilC to hide real joysticks to the game. The necessary files are provided in the download of this tool, but here is the link for more information. Read §3before installing anything.

I would like to thank "Shaul" for vJoy that allowed this software and many others (among them UCR and joystick Gremlin) to exist.

# 3 Setup

# 3.1 External tools setup

You will need to install Qt 5 and vJoy. For Qt 5 I will even recommend you to use Qt 5.11 with the MinGw C++ compiler (5.3.0 32 bits version) provided along with Qt, as this is exactly the one used to code this software. Hereafter I list the necessary Qt 5.11 components you will need to install to build and use all the tools available in UJPS:

"Preview" section: nothing needed

"Qt / Qt 5.11.0" section: MinGW 5.3.0 32 bits and Qt charts

"Tools" section: MinGW 5.3.0

Download the last version of vJoy. This software has been developed with the 2.1.8 release from November 2016, which still was the last release in beginning of 2018. If a new version is released, updating the "vJoy218SDK-291116" directory may be necessary and anyway advised. I would provide an update in this case.

https://www.qt.io/download-qt-installer http://vjoystick.sourceforge.net/site/index.php/download-a-install

# 3.2 Building the application

Once these 2 steps are done, do the following:

- Verify if Qt paths are included the "PATH" environment variable. To do so you can open a Windows console (cmd.exe) and type "set PATH".
  - if yes, open the "build\_ UJPS.bat" file as text (don't double-click on it) and remove the lines 3 to 6
  - o if not, modify the line 5 with the 2 Qt paths matching your own Qt setup. You should find a "qtenv.bat" file in the Qt directories that contains them
- Close the "build\_ UJPS.bat" and run it (double-click on it). It will compile and deploy all the components of the tool. It will not compile the provided profiles.

The "cleanAll.bat" allows you to clean all the binaries generated during the build process (.o, .exe files, makefiles, ...). You will come back in the same state after you downloaded the content of the repository. So the tool will not be runnable anymore except if you build the tool again.

# 4 A quick tour of the repository content

<u>CleanQtProjects:</u> a small home-made utility program that cleans (deleting binary files, makefiles, ... and all files that are created when building the project) a Qt project

<u>StaticLibs:</u> the source code shared by the different programs (UJPS, Monitoring and AxesCurves) and the profiles plugins is centralized here to avoid code repetition

<u>UjpsMainApp:</u>the main application, UJPS.exe, the one that runs profiles (§5)

Monitoring0/1/2: similar little programs that reflect joysticks inputs (§7):

- Monitoring0: as seen by QtGameController, that fully support POV
- Monitoring1: as seen by the class RealJoystick that transforms a POV into 4 buttons
- Monitoring2: as seen by the controllers plugins (see further on this page)

<u>ControllersPlugins:</u> the source code of the provided controllers plugins. These plugins brings the following services (§7):

- Definition of buttons and axes names
- Re-ordering of axes or buttons
- Addition of additional ("virtual") buttons, in addition of the ones added from POV
- Other services such as led support for Warthog throttle

<u>AxesCurves:</u> a utility program very useful to fine-tune the curves and dead-zones of the joysticks axes (see §16.1 for more details)

<u>HidingJoysticks:</u> 2 different ways to hide real joysticks from the game and even the system:

- Devreorder (§6.1)
- WhiteKnight (ViGEm) (§6.2)

vJoy218SDK-291116: the dll and lib files of vJoy. Useful for the compilation of the tool

Profiles: the example profiles I provide. You don't have to necessarily put yours here

RemoteControllers: an example of very basic remote controller I provide (§8)

# 5 The main window

The main window pops up when running "UJPS.exe". It is quite basic and provides the following functionalities:




Figure 2: UJPS main window

- browse to select the profile to run. You have to select the .pro file. The profile is not loaded right away
- select a time step. The default one is 15 ms. At each time step the data of real joysticks is read, transformed by the profile and the result is sent to virtual joysticks and / or keyboard
- shows the settings menu. You especially needs to specify the paths:
  - to your Qt installation to be able to compile profiles from the main window
  - to "vJoyConfig" executable to setup virtual joysticks within the program (not recommended, especially if you use several virtual joysticks)
- compilation: if you installed Qt with the MinGw compiler, you can use directly this feature to compile your profile without using an IDE or compile with the command line. But UJPS does not provide a text editor to modify the profile source code




Figure 3: compiler widget

- play button: run the profile / plugin. It is loaded when it is played if it is not already loaded. If another one is already loaded, it is unloaded before loading the new one
- stop button: stops the profile (the virtual will not be fed anymore) but does not unload it
- unload button: unloads the profile. It is not needed before selecting a new profile. It is useful
  to be able to recompile the profile currently loaded after a code modification (otherwise the
  profile compilation will fail because the dll cannot be rewritten) or to make the program
  aware that you connected a new joystick
- a text zone to send messages and errors

#### Here are a few probable errors you could encounter:

- an error when loading the profile. It can be due to several reasons:
  - o the file does not exist anymore or you don't have read access on it
  - the dll file specified is not a UJPS profile
- an error due to the initialization of the profile: if you activated "vJoyConfig.exe" in the settings menu and you did not run the program as an administrator
- any error due to programming issues in the profile that passed the compilation

# 6 Hiding the real joysticks

If you don't hide real joystick from the game, it will see the input from both a real joystick and a virtual joystick. It can be really annoying when assigning the controls in the game's controls menu.

#### 6.1 Devreorder

This method is the simpler one but it works only for the games that use the library Direct Input 8. You have to:

- copy the file "dinput8.dll" next to the game executable. Use the x64 version if the game executable is 64 bits compatible, otherwise use the x86 version
- copy the "devreorder.ini" file next to it to and edit it by placing the names of the joysticks you want to hide just after "[hidden]"

# 6.2 WhiteKnight and ViGEm

Run WhiteKnight.exe. The first time you will have to install HidGuardian and HidCerberus (ViGEm components) using the dedicated buttons in the GUI. It is fully done by WhiteKnight (no additional download or setup) and it only takes a few seconds.

Then start the service. At that time you can open the configuration (html) page by clicking the link. It opens in your default internet browser. Select the joysticks to hide, unplug them and replug them. If you don't modify these settings, you will not need to redo all the previous steps each time.



Figure 4: WhiteKnight GUI

Click on "Pick App" and click in the UJPS window. The PID (process ID) of UJPS.exe should appear in the configuration page after waiting a few seconds and a refresh. This step allows UJPS to see the joysticks, i.e. UJPS has been white-listed for these joysticks. The white-listing process uses PID, so it has to be done again each time you restart UJPS.exe.

If a profile is loaded, you need to unload and reload it so that it can see the joysticks that were white-listed.

# 7 Controllers plugins and monitoring apps

The base class for real input\* joysticks is "AbstractRealJoystick". "RealJoystick" is the standard class for real joysticks and contains a pointer to a QGameController object from the QtGameController module. "EnhancedJoystick" is a decorator class and add several features to an existing real joystick:

- axes curves and trims (see §16.1)
- buttons and axes locking (see §16.2)

You will not have to bother with all these classes as you will only have access to EnchancedJoystick objects.




Figure 5: real joysticks classes

The controllers plugins provide:

- In the INCLUDE directory: a name for each button and axis to be used in your profiles for having an understandable profile code
- In the SOURCES directory: a name for the each button and axis for display in Monitoring apps and AxesCurves (must be in sync with the previous names)
- It is possible to re-order axes and buttons
- It is possible to add "virtual" buttons, in addition of the ones added from POV
- It is possible to reimplement RealJoystick::setData (that does nothing), to send data to the joystick. It was useful for led support for Warthog throttle, and it can be for remote joysticks
- ...

For now I provide only a few plugins, because it needs to be tested to be sure that the names and the buttons or axes matches and I and my friends only own a few of them. But don't hesitate to contact me if you want that I do one for your controller. Just tell me with no ambiguity which physical axis/button matches which axis/button in Monitoring1 and what names you want, I will do the plugin and share with everyone. In the meantime you should not be blocked.

<sup>\*</sup>as you can also use remote controllers or virtual joysticks as inputs for UJPS.

The following images illustrate what can be seen for the Thrustmaster Warthog throttle with each of the 3 monitoring apps:

- Monitoring0 shows the 32 buttons and the POV, with no explicit axes names
- Monitoring1 shows 36 buttons and no POV, with no explicit names
- Monitoring2 shows 52 buttons, no POV and axes are re-ordered and have explicit names




Figure 6: Warthog throttle and monitoring apps

# 8 Remote controllers

# 8.1 The theory

Remote controllers are a way to further customize one's setup using screens. It is an application that can run on the same computer or on a tablet or mobile phone connected to the PC. The application uses the provided class "RemoteJoystickClient" to exchange data with the "RemoteJoystickServer" created in the UJPS profile. It often consists in touch-screens used as input-only devices. Remote controllers are also used by Roccat Power Grid or LEA extended input.

Just as any AbstractRealJoystick, such an object can send inputs as buttons and axes, and receive data from the function setData.

To implement one, on the profile side, you have to:

- Define an EnhancedJoystick pointer in the private section of Profile.h:
   EnhancedJoystick \*erj;
- In setupJoysticks, create the RemoteJoystickServer object. The function will block here
  waiting for you to connect the client (see further). To construct one you have to provide 4
  arguments:
  - Its name. It must be the same as the one sent by the client after it gets connected (see AbstractRemoteJoystickClient:: description), otherwise it will produce an error...
     it is done to check that the connected app is the expected one
  - o The port to use for the connection. It must be in sync with the one set in the client
  - The id of the joystick. I recommend you to use an index greater than 16 to avoid to use one already used by a real joystick
  - The time (in milliseconds) you let to the user to connect the remote joystick application before sending an error message. You can ignore this argument, in this case the default value will be 10 seconds

emit message("Now connect the client application for the remote controller", Qt::black);
RemoteJoystickServer \*rjs = new RemoteJoystickServer{"TouchScreen2",32241,100};
erj = this->registerRealJoystick(rjs);

Then you just have to use it like any other real joystick

On the client side you have to create your own GUI application, and I do not provide any GUI editor as Roccat or LEA extended input do. So, yes, it is not as easy as the rest of the tool. So you have to compose your own widget. On the joystick and network side, you just have to reuse the classes I provided in the example:

- Copy as it is AbstractRemoteJoystickClient
- Copy RemoteJoystickClient then adapt it to your needs
- Use ConnectionWidget to parameterize connection

# 8.2 A non-trivial example of what can be done

This example is here to illustrate the possibilities of UJPS when coupling real and remote joysticks, but this is only an example. So imagine you have one (yes, let's say only one, it will be hard enough ©) Thrustmaster MFD bezel, one screen behind (with no touch function) and you have no feedback from the game to display on the screen... but this does not mean that each button of the MFD must have only one function.

The screen (on which the remote joystick application is running) will display menus in which we will navigate using the bezel buttons. The profile will send the necessary info to the client so that it knows exactly what it has to render. And function of what the client displays, the profile must know that the inputs from the bezel does not have the same meaning. In fact, we could have an object in the profile that "synchronizes" the bezel and the screen. To simplify, we could do that with a state machine where one state matches a client MFD page and a bezel button action matches a transition or a virtual joystick action (depending on the state).




Figure 7: example of profile structure

We could even go further and when a shift button is pressed (see §11) on Joystick 2, use button of Joystick 1 to navigate the MFD page, for example with a 4 direction HAT with a press function.

I hope I convinced you that even with no feedback from the game it is possible to do interesting things with remote controllers. But obviously it can now be accessible only to the most courageous or geek ones.

And I hope I did not lost you, the rest of the manual is really easier!

# 9 Create a profile

# 9.1 Profile creation (by manual copy of a provided example)

This step is not yet automated by the main window, so for now you will need to do it manually:

- create a new directory next to the provided example. If you create it somewhere else, you will need to modify some paths in the .pro file
- copy the .pro file for the example. Rename it as you want. Open it and replace the line 2 (the one with "TARGET = ..."), by "TARGET = theNameYouWantForTheProfileDII"
- also copy the CODE directory of the example

# 9.2 Profile coding

The easier way to do it is to use one of the provided examples as a starting base. You have to create a class derived from AbstractProfile and implement the pure virtual functions "setupJoysticks" and "runFirstStep" and probably reimplement the virtual function "stop". Programmatically speaking, that is the only requirement.

#### function setupJoysticks

This function is executed every time the play button is pressed in the main window. It can be executed several times on the same object (but you have to press stop between 2 presses on play). Your implementation of this function should do the following operations:

- 1. Common to real and virtual joysticks:
  - a. In a private section of Profile.h, declare an EnhancedJoystick pointer for each real
    joystick (or remote one) and a pointer to a VirtualJoystick for each virtual joystick
    you will use in your profile.

```
EnhancedJoystick *tmwj; // for Thrustmaster Warthog Joystick
EnhancedJoystick *tmwt; // for Thrustmaster Warthog Throttle
VirtualJoystick *vj1; // virtual joystick #1
VirtualJoystick *vj2; // virtual joystick #2
```

o b. Initialize them at nullptr in the Profile constructor.

```
tmwj = nullptr;
tmwt = nullptr;
vj1 = nullptr;
vj2 = nullptr;
```

- 2. Setup the real joysticks:
  - a. In the setupJoysticks function, use the registerRealJoystick function to retrieve an EnhancedJoystick pointer to the real joysticks you are interested in. If you have no joystick with this description currently connected and recognized by the system, nullptr will be returned. To be sure to make a mistake in the spelling of the description, you can use the variable "Description" contained in the namespace corresponding to the controller you are interested in:

```
tmwj = this->registerRealJoystick("Joystick - HOTAS Warthog");
tmwt = this->registerRealJoystick(TMWT::Description);
```

 b. It is a good idea to send a message in the main window to keep the user aware of what is happening.

```
if (tmwj) {emit message("Warthog joystick detected !",Qt::black);}
else {emit message("Warthog joystick not detected !",Qt::red);}

if (tmwt) {emit message("Warthog throttle detected !",Qt::black);}
else {emit message("Warthog throttle not detected !",Qt::red);}

if (!tmwj || !tmwt) {return false;}
```

- 3. Setup the virtual joysticks:
  - a. Create the virtual joysticks. If the configuration fails, the constructor of VirtualJoystick throws an exception that is caught by the MainWindow which will display an error message.

```
vj1 = new VirtualJoystick{1};
```

 b. I recommend you to send a message to the main window using "emit message" to inform the configuration succeeded. At last, register the virtual joystick so that at each time step the virtual joystick object check if it is necessary (or not) to send an HID report. Otherwise the virtual joystick will not be refreshed.

```
emit message("Virtual joystick 1 configured",Qt::black);
this->registerVirtualJoystick(vj1);
```

o c. The steps a and b must be both done for virtual joystick 1 before doing it for the second one, and so on...

#### function runFirstStep

The first time step is dedicated to the definition of your mappings. To do so, process this way:

• 1. Register shift buttons for layers. For details about layers see §11.

```
this->registerLayerDim1(Layers::In, tmwt, TMWT::MSD);
this->registerLayerDim2(Layers::Up, tmwt, TMWT::BSF);
this->registerLayerDim2(Layers::Down, tmwt, TMWT::BSB);
```

• 2. It is advised to initialize the virtual joysticks buttons and axes taking into account the position of real joysticks buttons and axes so that they are in sync at the start. Otherwise maybe a movement will be needed to get them in sync. Here is a simple example:

```
vj1->resetReport();
vj1->setButton(VJOY::DX1,tmwj->buttonPressed(TMWJ::TG1));
vj1->setAxisValue(VJOY::Y,tmwt->axisValue(TMWT::THR_LEFT));
```

• 3. Create the initial mappings using the functions Map, MapButton, MapAxis, MapAxis1, ... that are explained further.

#### function stop

The default implementation of the stop function (AbstractProfile::stop) does the following:

- deletes all mappings and mappings modifications pending requests
- deletes info about layers configuration
- clear joystick changes
- delete all registered real and virtual joysticks

There is no strict need to reimplement the stop function, but you might want to do some additional things than the default implementation. In the next example, the stop function do the following:

- set the brightness of the Warthog throttle leds to 0
- call the default implementation to do the necessary cleaning (it is mandatory)
- reinitialize the deleted pointers to nullptr

# 9.3 Profile compilation

Programmers may not need advices on this point, especially if you use an IDE and that you integrated Qt into it. For others, if you use Qt 5 with a MinGw compiler (only slight adjustments should be needed for other compilers) you can:

- use the compilation widget of the main window (§5)
- compile your profile with a bat file (examples are provided for MinGw compiler)

## 10 What is under the hood

This part is essential for a full comprehension of the tool if you want to write your own triggers, actions or mappings.

UJPS relies on what we call "mappings". A mapping is a sort of connection between a real joystick event and a virtual joystick event. A profile includes a whole set of mappings and each mapping is tested at each time step. The different pre-defined mappings are explained in §14.

At each time step, the run function of AbstractProfile is run. It performs exactly the following steps:

- A. Read the events coming from every registered real joystick
- B. Compute the current layer given the shift buttons positions (see §11)
- C. For each real joystick event, look which mappings it triggers (only among the mappings that can be triggered by events), and for each triggered mapping, perform the associated action (only post events in a queue)
- D. Look for all triggered mappings (only among the mappings that can be triggered by "states", as contrary to "events") and for each triggered mapping, perform the associated action (only post events in a queue)
- E. Perform all the keyboard events (available only for Windows for now), and call setAxis and setButton functions of VirtualJoystick
- F. Call sendReport function of each registered virtual Joystick to send the new buttons and axes positions to the vJoy driver
- G. Process pending events. If a callback, from an ActionCallback (see §13.1.5), is called at step C or D, and if the callback contains calls to some Map or Unmap functions, the mappings are not deleted (only disabled) or added during C or D step, but now

Additional custom mappings, triggers and actions classes can be added to add new features to the software. To do so you have to sub-class respectively AbstractMapping, AbstractTrigger or AbstractAction. Before doing so, take a look at the existing one to understand how it works.

# 11 Layers and LayersCombos

# 11.1 LayersCombos as mapping filters

Each mapping is given only for a set of layers, called a "layers combo". It means that if the current layer is included in the layers combo of the mapping, the mapping can be triggered, otherwise it is not possible. The layer combo of the mapping acts as a filter.

The definition of a layer is the same of in Thrustmaster TARGET, but the way we use it is a bit different. In TARGET, when you map a button (for example), you have to specify the action for each layer and puts 0 for the layers where you want to do nothing. The following example should be clearer than a long speech:

# 11.2 Definition of a layer

The ones that are not used to Thrustmaster concept of layers should not have understand anything of the previous lines, this is perfectly normal. Now is time for more explanations. The layers in UJPS is implemented just as in TARGET and is not customizable profile by profile in the current version V1.0.0.

Layers can be seen as a way to give different functions to a same button / axis. It can be seen different ways: as shifting (as the shift or control keys of a keyboard) or as different "modes" (e.g. air/air or air/ground modes for military aircraft simulations). The implementation of the layers is 2-dimensional: one dimension with 2 possibilities "In" and "Out", another with 3 possibilities "Down", "Middle" and "Up". Don't focus on the names they are not really meaningful!

La	vors	Dim 1	
La	yers	Out	In
	Down	OD	ID
Dim 2	Middle	ОМ	IM
	Up	OU	IU

Figure 8: built-in fixed layers as in Thrustmaster TARGET

The default layer is Out / Middle. It is generally used as the layer when none of the "shift buttons" are pressed.

# 11.3 Registering shift buttons

To register a shift button, you have specify the dimension, the sub-layer, a pointer the real joystick and the number of the button. Usually you do so in the play function of the profile (Profile.cpp):

this->registerLayerDim1(Layers::In, tmwt, TMWT::MSD);

```
this->registerLayerDim2(Layers::Down, tmwt, TMWT::BSB); this->registerLayerDim2(Layers::Up, tmwt, TMWT::BSF);
```

It is also perfectly possible to define buttons for Out and Middle sub-layers, but to understand what can be the interest of it, look at the next part.

# 11.4 How is computed the current layer

The current layer is computed using the registered shift buttons, their associated sub-layer and the current state of these buttons. The exact algorithm, in pseudo-code, is the following:

```
// initialize with default
subLayer1 = Out;
subLayer2 = Middle;

for each d1 in dim1ShiftButtons // one item per call of registerLayerDim1
        if d1.button.isPressed
            subLayer1 = d1.subLayer1; break;

for each d2 in dim2ShiftButtons // one item per call of registerLayerDim2
        if d2.button.isPressed
            subLayer2 = d2.subLayer2; break;

currentLayer = (subLayer1,subLayer2);
```

So the priority is given to the shift button registered first. And if none of the registered buttons is pressed, the default sub-layer is used. If you understand exactly how the algorithm works, you can try to play more with "registerLayerDim1 and 2".

#### 11.5 Constructing LayersCombo

To specify a LayersCombo to a mapping, you have to construct one. Simple first: if you want that your mapping is activated for all layers, you can just provide "AllLayers". It is a global variable that covers all layers. To do so you can also provide a default-constructed LayersCombo. The 3 next lines are equivalent:

```
MapButton(tmwj, TMWJ::TG1, AllLayers, vj1, VJOY::DX1);
MapButton(tmwj, TMWJ::TG1, LayersCombo{}, vj1, VJOY::DX1);
MapButton(tmwj, TMWJ::TG1, {}, vj1, VJOY::DX1);
```

If you don't want to specify all layers in your LayersCombo, you have to initialize it with a string. The accepted characters are "i", "o", "d", "m", "u", "|" and you can spaces wherever you want. Please refer to table 1 when reading the following lines:

- "i" means ID, IM and IU (the "In" column)
- "o" means OD, OM and OU (the "Out" column)
- "io" means AllLayers
- "u" means OU and IU (the "Up" line)
- "m" means OM and IM (the "Middle" line)

- "d" means OD and ID (the "Down" line)
- "md" means OD, ID, OM and IM (the "Middle" and "Down" lines)
- "umd" means AllLayers
- ...

# And you can also combined several ones with a "|":

- "od | im" means OD and IM
- "od | id" is equivalent to "d"
- "md" is equivalent to "m|d"
- "im" means IM and is not equivalent to "i|m" that means ID, IM, IU and OM

# 12 Very basic axis and button mapping

### **MapButton and MapAxis**

To perform the simplest bindings, i.e. reproduce the state / value of a button / axis from a real joystick to a virtual one, you can simply call the "MapButton" and "MapAxis" functions:

```
MapButton(tmwj, TMWJ::H2L, AllLayers, vj1, VJOY::DX32);
MapAxis(tmwj, TMWJ::JOYX, AllLayers, vj1, VJOY::X, AxisDirection::Reversed);
```

Where tmwj is a pointer to the EnhancedJoystick embedding the Warthog joystick and vj1 a pointer to the virtual joystick 1. The first line links the H2L button of the Warthog joystick with the button 32 of the virtual joystick 1. And the second one links the JOYX axis to the X axis but reversed. Not to reverse, just specify "Normal" instead of "Reversed".

Be aware that if your profile only uses these 2 functions, there is strictly no interest to use UJPS... or any software for joystick programming.

#### **Unmapping**

You can also delete bindings by calling the following functions (from class AbstractProfile):

UnmapAll(); UnmapButton(tmwj,TMWJ::TG1); UnmapAxis(tmwj,TMWJ::JOYX);

## 13 Pre-defined actions

All action classes inherit from the AbstractAction class.

#### 13.1.1 Actions about buttons

## **ActionButtonSetChange**

The action ActionButtonSetChange reacts only to changes (on real joysticks) and uses the new real joystick button state to reproduce it on the button of the virtual joystick. It is useful to do a "simple button binding". To construct one you have to specify a pointer to the virtual joystick and the number of the button.

```
ActionButtonSetChange(VirtualJoystick*,uint)
```

To perform a "simple button binding", you can use one of the 2 following lines, they are exactly equivalent:

Any of these 2 instructions links directly the button H2L of the Warthog Joystick (pointed by tmwj in this example) to the button 128 of the first virtual joystick (pointed by vj1 in this example) for all layers.

#### ActionButtonSetChangeOpposite

The action ActionButtonSetChangeOpposite do the same but the value of the button of the virtual joystick will be the opposite of the value of the real joystick button.

```
Map(tmwj, ControlType::Button, TMWJ::H2L, AllLayers, new TriggerButtonChange{}, new ActionButtonSetChangeOpposite{vj1,VJOY::DX128} );
```

#### **ActionButtonToggle**

The action ActionButtonToggle is constructed using the same arguments but when activated this action inverts a virtual joystick button. This action is not meant to be activated so often (i.e. not at each time step for example) as otherwise the virtual joystick button will be toggled at each time step.

#### ActionButtonPulse

The action ActionButtonPulse is constructed using an additional argument, the number of cycles of the pulse. You can easily transform a time interval in milliseconds into a number of cycles using the ms2cycles function. This way, whatever the time step is (it is the time step specified in the main window) the pulse will last the same duration.

With the above line, when the H2L button is pressed (passes from up to down position, not is in the down position), a pulse of 500 ms on the 128th button of virtual joystick 1 is performed.

## ActionButtonPress and ActionButtonRelease

These 2 actions are used to press or release a button of a virtual joystick when activated. With this you can for example press a virtual button when one real button is pressed and release it when another real button is pressed:

## 13.1.2 Actions about axes

## **ActionAxisSetChange**

The action ActionAxisSetChange reacts only to changes (on real joysticks) and uses the new real joystick axis state to reproduce it on the axis of the virtual joystick. It is useful to do a "simple axis binding". Curves and trims are defined separately (see §16.1) but with this action you can reverse the direction. To construct one you have to specify a pointer to the virtual joystick, the number of the axis and the direction ("Normal" or "Reversed").

```
ActionAxisSetChange(VirtualJoystick*,uintvAxis, uintaxisDirection)
```

To perform a "simple axis binding", you can use one of the 2 following lines, they are exactly equivalent:

Any of these 2 instructions links directly the axis JOYX of the Warthog Joystick (pointed by tmwj in this example) to the axis X of the first virtual joystick (pointed by vj1 in this example) for all layers.

#### ActionAxisIncrement

The action ActionAxisIncrement is useful to create an axis from buttons.

```
Map(tmwj, ControlType::Button, TMWJ::H1L, AllLayers, new TriggerButtonPress{}, new ActionAxisIncrement(vj1,VJOY::Z, 0.05f));
Map(tmwj, ControlType::Button, TMWJ::H1L, AllLayers, new TriggerButtonState{true}, new ActionAxisIncrement(vj1,VJOY::Z, 0.01f));
Map(tmwj, ControlType::Button, TMWJ::H1R, AllLayers, new TriggerButtonPress{}, new ActionAxisIncrement(vj1,VJOY::Z,-0.05f));
Map(tmwj, ControlType::Button, TMWJ::H1R, AllLayers, new TriggerButtonState{true}, new ActionAxisIncrement(vj1,VJOY::Z,-0.01f));
```

With this example, the buttons H1L and H1R are used to control the axis Z of the virtual joystick 1. When H1L is pressed the value of the axis increases of 0.06, then it increases of 0.01 until the Z axis reaches the maximal value of 1 or until the H1L button is released.

#### 13.1.3 Actions about keyboard

As much as possible, you should prefer to use virtual joystick instead of keyboard actions. Indeed, if you have many keyboard actions, you will need to use modifiers, and some issues can arise. For example if you generates LCtrl+A and LShift+B, the game could also see more inputs: LCtrl+B and/or LShift+A. Keyboard actions are only supported on Windows for now.

#### ActionKeySetChange and ActionKeySetChangeOpposite

Just like ActionButtonSetChange and ActionButtonSetChangeOpposite, these 2 actions react only to changes. When a change is noticed on the source button, the key is changed accordingly (or oppositely). Modifiers can be used. The prototypes of the constructors are the following:

```
ActionKeySetChange(uint key, uint modifier = 0)
ActionKeySetChangeOpposite(uint key, uint modifier = 0)
```

In the file WindowsKeys.h, also available in the Annex (§20.4) you can find all the available keys names. Here is an example of code:

## ActionKeyPress, ActionKeyRelease and ActionKeyPulse

Just like ActionButtonPress, ActionButtonRelease and ActionButtonPulse, there are the analog actions for keyboard keys: ActionKeyPress, ActionKeyRelease and ActionKeyPulse. Modifiers can be used. There is no modifier by default. The prototypes of the constructors are the following:

```
ActionKeyPress(uint key, uint modifier = 0)
ActionKeyRelease(uint key, uint modifier = 0)
ActionKeyPulse(uint key, uint modifier = 0, uint cycles = 4)
Here is an example of code:

Map(tmwj, ControlType::Button, TMWJ::H3U, AllLayers,
new TriggerButtonPress{},
new ActionKeyRelease(Key_Tab,Key_LShift)
);
```

With this example, when the H3U button is pressed, the "Left Shift + Tab" keystroke is release. And when the H3R button is pressed, a pulse of 60 ms on the "M" key is performed.

## 13.1.4 Actions Chain, Delay and Sequence

The users of Thrustmaster TARGET scripts should recognize these actions. The definition is exactly the same as in Thrustmaster.

#### ActionChain

A chain action is useful to perform several actions at the same time. The actions are not done at the same only if you use a delay in the chain:

The above code performs a pulse on the "A" key and 150 ms later another one on the "B" key. If the time of the delay is smaller than the time of the first pulse, the "B" key gets pressed before the "A" key gets released.

#### **ActionSequence**

An sequence is used to generate different actions each time it is activated. Once all sub-actions have been performed, it starts again with the first one.

```
Map(tmwj, ControlType::Button, TMWJ::H1D, AllLayers, new TriggerButtonPress{}, new ActionSequence{ new ActionKeyPulse(Key_C,0,ms2cycles(60)), new ActionKeyPulse(Key_D,0,ms2cycles(60))} );
```

When you press several times the H1D button, it will generate pulses on "C" key the first time, "D" key the second time, "C" key the third time, ...

And you can combine chains with sequences at will...

#### 13.1.5 Executing a custom function

#### **ActionCallback**

The ActionCallback is used to execute a custom function when it is activated. It is the equivalent of the "EXEC" feature of Thrustmaster scripts. To construct one, you must provide a std::function object

(or something that can be converted to, such as a pointer to a function that takes no argument and has no return, or a compatible lambda).

```
ActionCallback(std::function<void()>)
```

Here is an example of use with both std::bind and a lambda for a Profile member function. Of course the same can be done with non-members functions be it has less interest:

```
void Profile::myMemberFunction()
        // just a few random instructions for the example
        DoAction(new ActionButtonPulse(vj1,VJOY::DX13));
        UnmapButton (tmwj, TMWJ::S4);
        MapButton (tmwj, TMWJ::S4, vj1, VJOY::DX1);
        vj1->setAxis(VJOY::Z,0f);
// with std::bind
Map(tmwj, ControlType::Button, TMWJ::TG1, AllLayers,
        newTriggerButtonPress{},
        newActionCallback(std::bind(&Profile::myMemberFunction,this))
);
// with a lambda
Map(tmwj, ControlType::Button, TMWJ::TG1, AllLayers,
        newTriggerButtonPress{},
        newActionCallback([this](){this->myMemberFunction();})
);
```

When the TG1 button gets pressed the member function "myMemberFunction" is executed. Here is another example with a lambda:

```
auto trimRandomY = [this](){tmwj->setAxisTrim(TMWJ::JOYY,((float)rand()/(float)RAND_MAX)*2.0f-1.0f);};

Map(tmwj, ControlType::Button, TMWJ::TG2, AllLayers, new TriggerButtonPress{}, new ActionCallback(trimRandomY));
```

In the above example, when the TG2 button gets pressed, the axis JOYY of the Warthog joystick is trimmed with a random value.

# 14 Pre-defined mappings

# 14.1 MappingStandard

A "standard mapping" uses one trigger and one action. When the current layer is in the mapping's layers combo and that the "trigger is triggered", the mapping performs its action. This is a very versatile mapping that can cover most of our needs, as they are already many different pre-defined triggers and actions and as you can easily create new ones. To use standard mapping, you have to use the "Map" function of the AbstractProfile class:

void Map(AbstractRealJoystick \*rj, ControlType type, uintrnum, LayersCombo, AbstractTrigger\*, AbstractAction\*);

The "ControlType" argument must be "Button" or "Axis" and "rnum" is the number of the button or axis.

# 14.2 MappingTempo

But we cannot do everything with a standard mapping. The "tempo" mapping can be only linked to real buttons, not axes. The principle is that if the button is pressed less than a given  $\Delta t$  the action1 is performed, otherwise once the button has been pressed during  $\Delta t$  the action2 is performed. To create one and append it to existing mappings, you have to use the "MapButtonTempo" function of AbstractProfile class:

voidMapButtonTempo(AbstractRealJoystick \*rj, uintrButton, LayersCombolc, uint cycles, AbstractAction\*act1, AbstractAction \*act2);

# 14.3 MappingAxis1

The "MappingAxis1" is equivalent to the "AXMAP1" of Thrustmaster TARGET. It is used to map one real axis to 2 virtual buttons. The axis is split in a given number of areas and:


- each time the axis changes of area for the one above, actionPlus is performed
- each time the axis changes of area for the one below, actionMinus is performed

To define the areas you can provide:

- a number: the areas will be distributed uniformly
- breakpoints defining the limits between the areas: N points means N+1 areas

MapAxis1(tmwj, TMWJ::JOYY, AllLayers, 5, actionPlus, actionMinus);
MapAxis1(tmwj, TMWJ::JOYY, AllLayers, {-0.9,-0.3,0.3,0.9}, actionPlus, actionMinus);

The following figure shows what is obtained when you ask for 5 points. You obtain the same thing if you provide the values {-0.8, -0.4, 0, 0.4, 0.8}.



# 14.4 MappingAxis2

The "MappingAxis2" uses the same splitting into areas than the "MappingAxis1" but there is no just 2 actions function of the direction of the movement, but one action per area: when the axis enters this area, the action of the area is performed. As for "MappingAxis1" you can provide the number of points or a list of breakpoints. If the number of points is different than the number of actions plus 1, an exception is thrown. It will be caught by the main window and everything that should have been done after is skipped.

# 14.5 MappingAxisRelative

This mapping makes an integration (mathematically speaking) of the real joystick axis to compute the virtual joystick axis value: when the real axis value is positive the virtual one increases and vice-versa. The virtual axis deflection is limited between -1 and 1. To use it you proceed as follows. The last argument is the time (in milliseconds) needed for the virtual axis to go from one extreme value to the other when the real joystick axis is at its extreme value.

```
MapAxisRelative(tmwj, TMWJ::JOYY, AllLayers, vj1, VJOY::Z, 4000.0f);
```

It performs exactly the following computation:

```
vAxisValue = \lim_{-1 \to 1} \left( vAxisValue + 2\frac{\Delta t}{T} rAxisValue \right)
```

where  $\Delta t$  is the time step and T the last parameter

#### 14.6 MappingMergeAxes

This mapping merges 2 axes into one, using weightings. In the following example, when at least one of the 2 brake pedals of the MFG crosswind moved, the Y axis of the first virtual joystick is set with the difference between the axes values of the 2 brake pedals (BRK\_LEFT and BRK\_RIGHT). A 0.5 is applied because the output must be in the range [-1,1].

MapMergeAxes(mfgx, MFGX::BRK\_LEFT, 0.5f, mfgx, MFGX::BRK\_RIGHT, -0.5f, AllLayers, vj1, VJOY::Y);

# 15 Pre-defined triggers for "standard mapping"

All trigger classes inherit from AbstractTrigger. The triggers does not know what button or axis they are watching, only the mapping has that information and give the trigger that info when calling the isTriggered function of the triggers. That is why we don't specify the real joystick and the axis / button number when creating a trigger.

# 15.1 Triggers about axes

#### **TriggerAxisChange**

Such objects are activated every time a physical axis moves. A trigger of this type is created when the "simple axis mapping" function "MapAxis" is called. The constructor takes no argument.

#### **TriggerAxisChangeComparison**

Such objects are activated every time a physical axis moves <u>and</u> that the comparison test is passed. The constructor is the following:

TriggerAxisChangeComparison(bool bGreaterThan, float threshold)

If "bGreaterThan" is true the comparison test is "> threshold", otherwise it is "< threshold".

# 15.2 Triggers about buttons

#### **TriggerButtonChange**

Such objects are triggered when the button is pressed or released. The constructor takes no argument. It reacts onlyto changes.

# <u>TriggerButtonPress</u> and <u>TriggerButtonRelease</u>

Such objects are triggered when the button is pressed / released. The constructor takes no argument. It reacts only to changes.

## **TriggerButtonState**

Such objects are triggered when the button is down (if true is provided to the constructor) or up (if false is provided to the constructor). The condition is evaluated at each time step. The constructor takes one argument, a Boolean.

```
Map(tmwj, ControlType::Button, TMWJ::H1L, AllLayers, new TriggerButtonPress{}, new ActionAxisIncrement(vj1,VJOY::Z, 0.05f));
Map(tmwj, ControlType::Button, TMWJ::H1L, AllLayers, new TriggerButtonState{true}, new ActionAxisIncrement(vj1,VJOY::Z, 0.01f));
Map(tmwj, ControlType::Button, TMWJ::H1R, AllLayers, new TriggerButtonPress{}, new ActionAxisIncrement(vj1,VJOY::Z,-0.05f));
Map(tmwj, ControlType::Button, TMWJ::H1R, AllLayers, new TriggerButtonState{true}, new ActionAxisIncrement(vj1,VJOY::Z,-0.01f));
```

# 16 Other features

#### 16.1 Axis trim and curves

The provided utility program "AxesCurves.exe" allows you to tune your curves and trims.

The function EnhancedJoystick::axisValue, which implements the pure virtual function AbstractRealJoystick::axisValue, returns the position of the axis taking the curve and the trim into account. If you need to access to the raw position of the axis, you can use the function EnhancedJoystick::rawAxisValue.

## **Axis trimming**

The curve is applied to the EnhancedJoystick objects. Their axes can also be trimmed but the virtual joysticks axes too. To better understand how it works, the final virtual joystick axis value is:

$$v2 = k * f(v1 + trim1) + trim2$$

#### Where:

- v1 is the raw (no curve no trim) position of the real axis
- trim1 is the trim of the real axis
- trim2 the trim of the virtual axis
- f the curve
- k is 1 or -1 function of the axes mapping direction (1 if Normal, -1 if Reversed).

So real axis trimming and virtual axis trimming are not the same thing. If you visualize the curve in a plot with the raw value v1 in abscissa and v2 in ordinate:

- real axis trimming moves the curve left/right
- virtual axis trimming moves the curve up/down

Real axis trimming is for example useful to compensate for a stick non perfectly centered. The function takes 3 arguments:

```
tmwj->setAxisTrim(TMWJ::JOYX,0.01f,AbsoluteOrRelative::Absolute); // set the trim at 0.01 vj1->setAxisTrim(VJOY::X,-0.2f,AbsoluteOrRelative::Relative); // subtract 0.2 to the trim
```

For example, to compensate for Warthog joystick centering inaccuracy you can use the 2 following code lines in a callback (see §13.1.5). This way, the current position of the joystick becomes the new zero position:

```
tmwj->setAxisTrim(TMWJ::JOYX,-tmwj->axisRawValue(TMWJ::JOYX));
tmwj->setAxisTrim(TMWJ::JOYY,-tmwj->axisRawValue(TMWJ::JOYY));
```

#### <u>Curves</u>

The curves are applied to the real joystick objects axes (whose class is EnhancedJoystick). You can add your own curves by sub-classing "AbstractCurve". To set a curve to the axis, you just have to:

tmwj->setCurve(TMWJ::JOYX,pointerToTheCurve);

And you can remove the curve by doing one of the 2 following:

```
tmwj->removeCurve();
tmwj->setCurve(nullptr);
```

If you set a curve, the previous one (if any) will be deleted.

#### **Pre-defined curves**

3 curves are pre-defined. They are the same as in Thrustmaster TARGET:

- Custom curves defined by breakpoints
- J curves with one "zoom" parameter (float type)
- S curves with parameters (all are float types):
  - o lower, center and upper dead zone
  - o "curve" parameter
  - o zoom

You can use the provided program "AxesCurves.exe" to tune the parameters of your curves. You can also add new curves to the program (C++ and Qt coding).




Figure 10: J curves with different zoom (left) and S curves with different "curve" (right)

For practical reasons, 3 functions are defined to set custom curves. They just create the new curve of the correct type with the given parameters and call setCurve:

```
tmwj->setSCurve(TMWJ::JOYX, lowerDZ, centerDZ, upperDZ, curve, zoom);
tmwj->setJCurve(TMWJ::JOYX, zoom);
tmwj->setCustomCurve({-1,-1, 0,0.2, 1,1});
```

Also for practical reasons, to create the custom curve, you have to specify a std::vector of floats. If the number of values is odd, an exception is thrown (it will be caught by the main window that will display an error message and of course no curve will be applied).

## The "AxesCurves" additional program

This program allows you to finely tune the parameters of your curves using a GUI. Using the current position of you joystick (the purple point) and the "real joystick trim", you can also re-center your controllers that need it. Only the J and S Thrustmaster curves are implemented for now.




Figure 11: AxesCurves main window

## 16.2 Button and axis locking

Both real and virtual joysticks can have their buttons and axes locked. In many cases it will not make any difference to lock the real or virtual button / axis, but in other cases it can be really useful. So not to limit the possibilities of the software, both are possible.

When you lock a real joystick button or axis, the software will not see any modification of the button state or the axis value even if the real one has changed and if you call the function "buttonPressed" or "axisValue", you will get the last value before locking.

```
tmwj->setButtonLocked(TMWJ::TG1,true);
tmwj->setAxisLocked(TMWJ::JOYX,true);
```

If you lock a button or an axis of a virtual joystick, it will be frozen. Once unlock, if nothing is sent to this button / axis, its state remains the same.

```
vj1->setButtonLocked(VJOY::DX1,true);
vj1->setAxisLocked(VJOY::X,true);
```

#### 16.3 DoAction

The function "DoAction" of the class AbstractProfile is useful to perform an action, from a callback from example. It is quite equivalent to the "ActKey" function of Thrustmaster TARGET but really more powerful as it can perform any action. But for some actions, there is no need to use DoAction. Here is an example:

```
DoAction(new ActionButtonPress{vj1, VJOY::DX1}); vj1->setButton(VJOY::DX1, true);
```

By default the action is deleted after performed. If you don't want to delete it, provide false as a second argument.

Using a chain action and a delay, it can replace the "DeferCall" function of Thrustmaster TARGET. In the following example, the function "myCallback" will be executed 1 second after this call to DoAction.

# 17 Current limitations and possible improvements

- Tool only works on Windows, mostly because vJoy is only available on Windows. Moreover ViGEm will only work on Windows too.
- Full integration of ViGEm into the UJPS main app. I will wait for the next version of it before doing anything. In the meantime WhiteKnight works really fine.
- Add new settings in the settings menu to ease the use of the main program.
- Add new features, as e.g. a new mapping "split axis" to split one real axis into 2 virtual axes... but don't forget that you can define your own ones!
- For now the creation of new profiles is done manually. It would be possible to automate it more in future versions.
- Currently the possible layers are fixed (2 dimensions with I/O and U/M/D). Even if I see no need to add give the choice for more dimensions, it may be possible to need more than 3 possibilities for a given sub-layer... even if too much complexity on this ground should harm ergonomics of the profile.

# 18 Dependencies, credits, useful links

vJoy, the tool that makes all this possible, from ShaulEizikovich.

http://vjoystick.sourceforge.net/site/index.php/download-a-installhttps://github.com/shauleiz/vJoy

Qt 5, a C++ general library. It was really helpful for GUIs, network (for remote controllers), static libs and plugins creation.

https://download.qt.io/archive/qt/5.7/5.7.1/

QtGameController, a non-official Qt module from Matthew Wellings:

https://github.com/openforeveryone/QGameController

Devreorder from Brian Kendall, for hiding joysticks (DirectInput8 only):

https://github.com/briankendall/devreorder

WhiteKnight from evilC, an integration of the current version of ViGEm:

https://autohotkey.com/boards/viewtopic.php?t=34890

ViGEm from Benjamin Höglinger:

https://github.com/nefarius/ViGEm (current version)

https://github.com/ViGEm/HidGuardian (next version in progress)

UCR (Universal Control Remapper) from Snoothy and evilC:

https://github.com/Snoothy/UCR

https://autohotkey.com/boards/viewtopic.php?t=12249

Joystick Gremlin from WhiteMagic:

https://github.com/WhiteMagic/JoystickGremlin

https://whitemagic.github.io/JoystickGremlin/

FreePIE from Anders Malmgren:

https://github.com/AndersMalmgren/FreePIE

http://andersmalmgren.github.io/FreePIE/

Damien, my tester for TWCS throttle and Logitech Extreme 3D plugins.

# 19 Changes notes

#### V1.1.0

- renaming of the tool for "UJPS C++"
- addition of the "AxesCurves" program to tune axes curves
- change of icons to use only free icons
- S curve computation correction
- addition of the "unload profile" feature in the main program
- few minor code changes

#### V1.2.0

- addition of "devreorder" release files (tool from Brian Kendall to hide real joysticks)
- addition of a compilation tool in the main program (only if QtMinGw compiler installed)
- now you have to provide the path to the .pro file when opening a profile, instead of to the dll file. This way you can open a profile before it has been compiled for the first time
- addition of a settings menu in the main program
- specifying the path to vJoyConfig.exe in the main program (instead of in profiles)
- solved a bug where the profile did not want to load again after unloading
- addition of the "Merge Axes" mapping
- a few minor code changes

#### **V2.0.0**

- centralize the repeated code for real joystick into the "realJoysticks.dll" lib and the "Controllers plugins"
- split "Monitoring" into "Monitoring1" and "Monitoring2"
- first iteration of the "remote controllers"
- possibility not to use "vJoyConfig.exe" in the main program (recommended)
- another correction in the loading / unloading process for profiles. Now you choose the profile by providing the path to the .pro, not the .dll
- addition of the "relative axis" mapping
- automatic creation of shortcuts in the deployment bat file

# **V2.0.1**

Important correction of curves and trim in AxesCurves

#### V2.1.0

- Modification of QtGameController to directly transform a POV into 4 buttons. The controllers
  plugins have been modified accordingly
- Added release files of WhiteKnight.exe, a little program from evilC that integrates HidCerberus and HidGuardian. It was added in the "HidingJoysticks" directory where was also moved the "devreorder" release files
- Improvement in deployment file

#### V2.1.1

Modification of QtGameController to fully support POV (see this in the new Monitoring0).
 Now this is the class RealJoystick that transform a POV into 4 additional buttons. The controllers plugins have been modified accordingly

## **V2.1.6 (skipping the intermediate versions)**

- Addition of LED support for Warthog throttle using the setData member function. It uses the Windows HID library. Windows setupapi.lib and hid.lib have been added so that you can build the Warthog throttle plugin without needing to install the Windows SDK
- Move Warthog throttle LED support to another thread to avoid slowing down the main loop
- Modification of RealJoysticksManager to be able to use several joysticks with the same name
- Important modification in the profile initialization to solve initialization issues. Before that a
  call to "buttonPressed" or "axisValue" on a RealJoystick in Profile::init could send false
  results. Moreover incorrect joysticks changes were sent between at the second time step
  only because the joystick state at the first step was not correct. This modification includes a
  modification of the interface of AbstractProfile

#### V2.2.0

• elevation of programming level (so it involves modifications in the profile interface) for real and virtual joysticks setup

#### V2.2.1

• deployment fixes and documentation update (Qt 5.11 instead of Qt 5.7): more details about the needed components of the Qt installation

#### V2.3.0

- improvements in build bat files
- minor modifications in code to remove compilation warnings
- addition of tooltips for buttons names in Monitoring apps
- removal of code repetition in controllers plugins (you will to make a few modifications in your profiles if you coded some before this modification. Look at provided examples)
- addition of T16000M and Xbox 360 controller plugins
- addition of the Description variable in "controllers plugins namespaces" to avoid to make an error in joystick description name when calling AbstractProfile::registerRealJoystick
- VirtualJoystick construction modification: only 1 argument needed (the vJoy device index) if you configure your vJoy devices outside of UJPS using vJoyConfig (recommended). Default values of 128 and 8 are provided for numbers of buttons and axes (only if "use vJoyConfig.exe" is checked in the settings menu, not recommended)

## 20 Annexes

# 20.1 List of pre-defined triggers

- TriggerAxisChange
- TriggerAxisChangeComparison
- TriggerButtonChange
- TriggerButtonPress
- TriggerButtonRelease
- TriggerButtonState

# 20.2 List of pre-defined actions

- ActionAxisIncrement
- ActionAxisSetChange
- ActionButtonPulse
- ActionButtonPress
- ActionButtonRelease
- ActionButtonSetChange
- ActionButtonSetChangeOpposite
- ActionButtonToggle
- ActionCallback
- ActionChain
- ActionSequence
- ActionKeyPress
- ActionKeyRelease
- ActionKeyPulse
- Delay

# 20.3 List of pre-defined mappings

- MappingStandard
- MappingTempo
- MappingAxis1
- MappingAxis2
- MappingAxisRelative
- MappingMergeAxes

# 20.4 Keyboards keys names (Windows)

This list has been established using the values available here: https://msdn.microsoft.com/fr-fr/library/windows/desktop/dd375731(v=vs.85).aspx

```
namespace Keys
       // modifiers
       const uint Key_LShift = 0xA0;
       const uint Key_RShift = 0xA1;
       const uint Key_LCtrl = 0xA2;
       const uint Key_RCtrl = 0xA3;
       const uint Key_LAlt
                               = 0xA4;
       const uint Key_RAlt
                               = 0xA5;
       // arrows
       const uint Key_ArrowLeft = 0x25;
       const uint Key_ArrowUp
                                       = 0x26;
       const uint Key_ArrowRight = 0x27;
       const uint Key_ArrowDown = 0x28;
       // special keys
       const uint Key_Backspace = 0x08;
       const uint Key_Tab
                             = 0x09;
       const uint Key_Return = 0x0D;
       const uint Key_CapsLock = 0x14;
       const uint Key_Escape = 0x1B;
       const uint Key_Space = 0x20;
       const uint Key_PageUp = 0x21;
       const uint Key_PageDown = 0x22;
       const uint Key_Insert = 0x2D;
       const uint Key_Delete = 0x2E;
       // digits (the ones that are above letters)
       const uint Key_0 = 0x30;
       const uint Key_1 = 0x31;
       const uint Key_2 = 0x32;
       const uint Key_3 = 0x33;
       const uint Key_4 = 0x34;
```

const uint Key\_5 = 0x35;

```
const uint Key_7 = 0x37;
const uint Key_8 = 0x38;
const uint Key_9 = 0x39;
// letters
const uint Key_A = 0x41;
const uint Key_B = 0x42;
const uint Key_C = 0x43;
const uint Key_D = 0x44;
const uint Key_E = 0x45;
const uint Key_F = 0x46;
const uint Key_G = 0x47;
const uint Key_H = 0x48;
const uint Key_I = 0x49;
const uint Key_J = 0x4A;
const uint Key_K = 0x4B;
const uint Key_L = 0x4C;
const uint Key_M = 0x4D;
const uint Key_N = 0x4E;
const uint Key_O = 0x4F;
const uint Key_P = 0x50;
const uint Key_Q = 0x51;
const uint Key_R = 0x52;
const uint Key_S = 0x53;
const uint Key_T = 0x54;
const uint Key_U = 0x55;
const uint Key_V = 0x56;
const uint Key W = 0x57;
const uint Key_X = 0x58;
const uint Key_Y = 0x59;
const uint Key_Z = 0x5A;
// numpad
const uint Key_Numpad0 = 0x60;
const uint Key_Numpad1 = 0x61;
const uint Key_Numpad2 = 0x62;
const uint Key_Numpad3 = 0x63;
const uint Key_Numpad4 = 0x64;
const uint Key_Numpad5 = 0x65;
```

const uint Key\_6 = 0x36;

```
const uint Key_Numpad6 = 0x66;
const uint Key_Numpad7 = 0x67;
const uint Key_Numpad8 = 0x68;
const uint Key_Numpad9 = 0x69;
const uint Key_NumpadMultiply = 0x6A;
const uint Key_NumpadAdd
                              = 0x6B;
const uint Key_NumpadSubstract = 0x6D;
const uint Key_NumpadDecimal = 0x6E;
const uint Key_NumpadDivide = 0x6F;
const uint Key_NumpadNumlock = 0x90;
// F keys
const uint Key_F1 = 0x70;
const uint Key_F2 = 0x71;
const uint Key_F3 = 0x72;
const uint Key_F4 = 0x73;
const uint Key_F5 = 0x74;
const uint Key_F6 = 0x75;
const uint Key_F7 = 0x76;
const uint Key_F8 = 0x77;
const uint Key_F9 = 0x78;
const uint Key_F10 = 0x79;
const uint Key_F11 = 0x7A;
const uint Key_F12 = 0x7B;
const uint Key_F13 = 0x7C;
const uint Key_F14 = 0x7D;
const uint Key_F15 = 0x7E;
const uint Key_F16 = 0x7F;
const uint Key F17 = 0x80;
const uint Key_F18 = 0x81;
const uint Key_F19 = 0x82;
const uint Key_F20 = 0x83;
const uint Key_F21 = 0x84;
const uint Key F22 = 0x85;
const uint Key_F23 = 0x86;
const uint Key_F24 = 0x87;
```

}